

How to Stop and Start the Print Spooler on Windows 10


For your personal home computer or any other computer on which you have administrative access, you can use the standard way described in option 1 below.

On a Windows 10 computer managed by MSB Computer Services, you may not have the administrative access required to make the required changes. In that case, please use option 2.

If you encounter any problems, please submit a request for Tech Support [online](#) or call Tech Support at 232-6616.

1. Standard way to stop (and restart) the Print Spooler on any Windows 10 Computer

- Click the Search Icon (magnifying glass) next the Start Menu in the lower left corner of your desktop.
- Type "Services", and from the search results, open the `Services` application.
- Right click on "services" and choose to "run as an administrator" and enter your administrative credentials.
- In the Services window, scroll down to the **Print Spooler** service and click it to open its properties window.
- In the properties window, on the **General** tab, move to the second section titled **Service status** section and click the **Stop** button in order to stop the service.
 - If you receive an access denied error on a Computer managed by MSB Computer Services, please use option 2 below.
- Also change the startup type to **Disabled** to keep the service from automatically starting when the computer boots up.
- To restart the Spooler, change the startup type back to **Automatic** and then click the **Start** button.



2. How to stop (and restart) the Print Spooler on a Windows 10 Computer managed by MSB Computer Services

- Make sure you are connected to the [UT VPN](#).
- Click the Search Icon (magnifying glass) next the Start Menu in the lower left corner of your desktop.
- Type "Software Center", and from the search results, open the Software Center application.
 - If you do not find Software Center on your computer, please submit a request for Tech Support [online](#)
- In Software Center, select the Applications tab, and then click the icon for **MSB_PrintSpooler_Service**.
 - If you do not see **MSB_PrintSpooler_Service** or something similar, please submit a request for Tech Support [online](#)
- In the **MSB_PrintSpooler_Service** Windows click **Install** to run the installer (the button will read **Reinstall** if you had run it once before already)
 - If you receive a message that the update failed, then please log out then log back in, reconnect to the VPN, and try once more.
- Each time you run this installer you will be prompted to *DISABLE* the Print Spooler (if it is currently running) or to *ENABLE* it (if it is currently stopped).

Software Center

CBACC McCombs School of Business

Applications

Updates

Operating Systems

Installation status

Device compliance

Options

All Required

Filter: All

Sort by: Most recent

New

MSB_PrintSpooler_Service

CBACC McCombs School of Business

Applications

Updates

Operating Systems

Installation status

Device compliance

Options

Applications > Application details



MSB_PrintSpooler_Service

Reinstall

Status: **Installed**
Date published: 7/1/2021

Restart required: No
Download size: Less than 1 MB
Estimated time: Not specified
Total components: 1

Enable/Disable Print Spooler



Print spooler current status is Running. . .
Do you want to DISABLE it?

Yes

No

Cancel